

目录

1. VPN概述	1
2. 下载客户端	1
3. 安装客户端	1
4. 客户端拨号	2

VPN使用指南

Linux版



1. VPN概述

VPN即虚拟专用网络，通过在Internet传输建立专用网络、确保数据在Internet传输中保证数据的可靠性、完整性、私密性。在家或移动办公的用户通过VPN拨号认证可以访问公司内部网络资源（OA、WIKI等）。

2. 下载客户端


- 浏览器打开<https://vpn-download.bianlifeng.com>下载对应版本客户端

3. 安装客户端

- 安装下载客户端

```
$ cd Downloads
$ tar -xvf anyconnect-predeploy-linux-64-4.1.02011-k9.g

$ cd anyconnect-4.1.02011/vpn
$ sudo ./vpn_install.sh
```



```
to collection, use, processing and storage of Personal Information and other data by Cisco Systems, Inc. (Cisco) and its affiliates for the purpose of providing you with the Software and its features, and for the purpose of improving the Software and its features. You consent to the collection, use, processing and storage of Personal Information and other data by Cisco and its affiliates for the purpose of providing you with the Software and its features, and for the purpose of improving the Software and its features.

Consent to Data Collection and Use. By using the Software and storage of your Personal Information and other data by Cisco (as defined in section 4 below). You also agree that Cisco and its affiliates may collect, use, process and store your Personal Information and other data in the United States and other countries.

. Privacy Statement. By entering into this Agreement, You agree to the Privacy Statement located at: http://www.cisco.com/web/siteassets/legal/privacy\_full.html

Description of Other Rights and Obligations

Please refer to the Cisco Systems, Inc. End User License Agreement located at: http://www.cisco.com/en/US/docs/general/warranty/English/EU1KEN.pdf


Do you accept the terms in the license agreement? [y/n] y
You have accepted the license agreement.
Please wait while Cisco AnyConnect Secure Mobility Client is being installed.
Starting Cisco AnyConnect Secure Mobility Client Agent...
Done!
sensetime@sensetime-To-be-filled-by-O-E-M:~/Downloads/anyconnect-4.1.02011-k9$
```

4. 客户端拨号

```
$ sudo ./vpnuir
```

打开客户端

- 选择右边小齿轮，去除 “Block connections to untrusted servers”



- 点击 Connect Anyway



- 输入域名 vpn.bianlifeng.com，选择Connect
- 输入蜂语/HR账号认证（如姓名张三：用户名：san.zhang密码：xxx）

- 断开VPN与退出程序
打开客户端点击Disconnect，VPN断开，客户端不会退出
右击客户端点击Quit，VPN断开同时退出客户端

